

# SMARTS Server Environment Internal Macro Description

This document contains information on the SMARTS Server Environment Internal Macro.

This document covers the following topics:

- ATTACH Function
  - CANCEL Function
  - CMTIMR Function
  - ABEXIT Function
- 

## ATTACH Function

ATTACH is used to create new units of work in the SMARTS server environment

Return Code	Feedback Code	Description
0	>0	A new unit of work was created but did not initialize successfully. Check for other errors in the log to determine why the new unit of work could not initialize successfully.
4	-	Insufficient TIBs available in the system. The resources in the SMARTS server environment must be increased.
8	-	Program to be started was not found. This implies an error in the installation of SMARTS as the PAENSTRT module could not be loaded in the SMARTS instance.
12	-	Security error. This should not occur and should be reported to your Software AG technical support representative.
16	-	Invalid program name. This should not occur and should be reported to your Software AG technical support representative.
20	-	Insufficient space to create a new unit of work. The resources in the SMARTS server environment must be increased.

## CANCEL Function

CANCEL is used to cancel a unit of work in the SMARTS server environment

Return Code	Feedback Code	
>0	-	Insufficient space available to cancel the unit of work. The resources in the SMARTS server environment must be increased.

## CMTIMR Function

CMTIMR is used to add and delete internal timers in the SMARTS server environment

Return code	Feedback Code	Description
4	-	Requested storage queue not found. This should not occur and should be reported to your Software AG technical support representative.
8	-	Insufficient space available to set the timer. The resources in the SMARTS server environment must be increased.

## ABEXIT Function

ABEXIT is used to add and delete termination exits in the SMARTS server environment

Return code	Feedback Code	Description
4	-	No previous exit found. This should not occur and should be reported to your Software AG technical support representative.
8	-	Insufficient space available to set an exit. The resources in the SMARTS server environment must be increased.
12	-	Invalid parameters. This should not occur and should be reported to your Software AG technical support representative.