


SOA Gateway Server Admin

Most tasks will be handled by the SOA Gateway Control Center, which presents a coordinated graphical view of the server. Tasks that are not possible from the Control Center are documented here.

- Stopping / Starting SOA Gateway Server - Windows
 - Stopping / Starting SOA Gateway Server - z/OS
 - Stopping SOA Gateway Server - z/VSE
 - Stopping / Starting SOA Gateway Server - Linux, AIX and Solaris
 - Updating an expired license
-

Stopping / Starting SOA Gateway Server - Windows

The SOA Gateway server runs from within the Apache webserver. You may see a new icon in the system tray



If not, start the program `[SOA Gateway Install Directory]\Apache\bin\ApacheMonitor.exe`.

Clicking on this symbol will give you the option to choose your SOA Gateway Server and the options **Start**, **Stop**, and **Restart**. **Start** or **Stop** will be greyed out depending on the status of the SOA Gateway.

The green arrow above indicates that the SOA Gateway is up and running.

If the SOA Gateway is not running the icon looks like this



Stopping / Starting SOA Gateway Server - z/OS

The SOA Gateway can be stopped by issuing `"/p jobname"` at the terminal.

To start the SOA Gateway, re-submit the ASGSTRT job.

Stopping SOA Gateway Server - z/VSE

- Bring up the Attention Routine prompt for the SOA Gateway partition by issuing the AR command *MSG <ASG_partition_ID>*
- Shut down the server with the command *<ASG_partition_reply_id> EOJ*

Stopping / Starting SOA Gateway Server - Linux, AIX and Solaris

As the SOA Gateway runs within Apache, bring down Apache to stop the SOA Gateway. Use the `apachectl` command, which will be located in the `[INSTALL_HOME]/apache2/bin` directory of your SOA Gateway installation. To start the server, issue the same command again with `start` as the first parameter.

Updating an expired license

If the SOA Gateway license has expired, please follow these steps to upgrade your license.

- *Linux/Solaris/HP/AIX* : Replace the existing *RisarisLicense.xml* in `[INSTALL_HOME]/config`
- *Windows* : Replace the existing *RisarisLicense.xml* `[INSTALL_HOME]/configuration`
- *z/OS* : Replace existing `INSTALL.HOME.CONF(ASGLIC)` and submit `INSTALL.HOME.JCL(SOAGINS4)`.